


PRESETTER E46L / E46LTW / E46LA / E46LTWA AGGIORNAMENTO SOFTWARE

WARNING: to perform this procedure you need to know the system password; check what the system password is in the instruction manual.

1) Check the software version currently installed on your presetter:

- access the "Configuration" menu and view the version number of the software.



2) Connect to the website www.elbocontrolli.com and download the latest software update available:

- access the technical support page from which the software can be downloaded
- check if there is a more recent software version for the presetter model you are using
- check the innovations introduced and any notes of compatibility with previous versions
- download the update file (in some cases it may be necessary to register on the site to download the file).

3) Copy the software update file on a USB stick:


- verify that the name of the downloaded file is of the type "e46l_upgrade_x.y.z.tar.gz"
 - x.y.z" represents the version number
 - (example: the file "e46l_upgrade_6.2.0.tar.gz" contains the software version 6.2.0)
- the USB stick must:
 - have a name without spaces or special characters (*, +, ?, !, \$, £, &, etc ...)
 - be formatted FAT32
 - only contain the downloaded update file.



4.1) Insert the USB device into one of the available presetter ports and wait for the update procedure to start automatically:



- press "OK" to start the procedure or the red "X" on the top left bar to cancel it.

ATTENTION: if the window to start the procedure does not appear, also proceed to point 4.2, otherwise go to step 5.



4.2) If the update procedure does not start automatically, perform the following steps to manually execute it:

- close the presetter application and display the machine desktop
- copy the update file from the USB device to the desktop
- click with the right mouse button on the file you just copied, then select "Extract Here" in the drop-down menu; a directory is created with the same name as the update file where the files contained in the package are extracted
- access the contents of the folder and double click on the "install_update.run" file to start the procedure.



5) Perform the update procedure; at the end remove the USB device and restart the application.

- the procedure requires the system password to complete the installation.

